

Free Crochet Pattern Lion Brand® Lion Suede - Wool-Ease®Chunky **Crochet Handbag Pattern Number:** 50942



Free Crochet Pattern from Lion Brand Yarn Lion Brand® Lion Suede - Wool-Ease®Chunky Crochet Handbag

Pattern Number: 50942

SKILL LEVEL: Advanced Intermediate

SIZE: One Size

Width 21 in. [53.5 cm] at base

Height 20 in. [51 cm] including handles

CORRECTIONS: None

MATERIALS

- 210-098 Lion Brand Lion Suede: Ecru
 - 4 Skeins (A)
- 630-099 Lion Brand Wool-Ease Chunky: Fisherman
 - 1 Skeins (B)
- Lion Brand Crochet Hook Size J-10
- Lion Brand Crochet Hook Size K-10.5
- · Lion Brand Stitch Markers
- Large-Eye Blunt Needles (Set of 6)
- Additional Materials

Rattan U-shaped purse handles, 12 in. [30.5 cm] at base

GAUGE:

8 sts + 9 rows = 4 in. [10 cm] in sc (single crochet) with larger hook using 1 strand each of A and B held together. BE SURE TO CHECK YOUR GAUGE.

PURSE SIDE (make 2)

With larger hook and 1 strand each of A and B held together, ch 49.

Row 1 (RS): Sc into the 2nd ch from hook and in each ch across - 48 sc. Turn each row.

Rows 2-14: Ch 1, sc in each sc across.

Row 15: Ch 1, sc in 3 sc, (skip 3 sc, insert hook from back to front around the next (4th) sc and pull up a loop, insert hook from front to back around first skipped sc and pull up a loop, yo and pull through 3 loops on hook – pleat made), (sc in next 2 sc, make pleat) twice, sc in 10 sc, (make pleat, sc in next 2 sc) twice, make pleat, sc in last 3 sc – 30 sc with 6 pleats.

Row 16: Ch 1, sc in each sc across. Place st markers at beginning and end of this row – 30 sc.

Row 17: Ch 1, sc into back loop of each sc across – 30 sc.

Rows 18-23 Ch 1, sc in each sc across.

Fasten off.

HANDLES

With smaller hook and A, sc around handles to cover. Fasten off.

HANDLE STRAPS (make 4)

With smaller hook and A, ch 17.

Row 1: Sc into the 2nd ch from hook and in each ch across - 16 sc. Turn.

Row 2: Ch 1, sc in each sc across. Do not fasten off. Turn.

Edging

Sc evenly around entire strap, working 2 sc in each corner, join with a slip st to first sc of edging. Fasten off.

CLOSURE STRAP

With smaller hook and A, ch 10.

Row 1: Sc into the 2nd ch from hook and in each ch across – 9 sc. Turn each row.

Row 2: Ch 1, sc in each sc across.

Row 3: Ch 6, sc in each sc across.

Row 4: Ch 1, sc in each sc across. Do not fasten off.

Edging

Sc evenly around entire strap, working 2 sc in each corner and 8 sc in the ch-6 loop, join with a slip st to first sc of edging. Fasten off.

BUTTON

With larger hook and 1 strand each of A and B held together, ch 5."

Rnd 1: Work 8 sc into 3rd ch from hook, join with a slip st to first sc. Fasten off. Pull unworked ch sts tightly.

ASSEMBLY

With RS together and WS facing, pin sides together. With larger hook and 1 strand each of A and B held together, sc evenly through both sides, beg at stitch markers, down side, around the bottom and up the other side to second set of stitch markers to join. Fasten off. Turn purse to RS.

Purse Edging

With larger hook and 1 strand each of A and B held together, sc evenly around opening, join with a slip st to first sc. Fasten off.

Thread each handle strap through a purse handle. With A, whipstitch handle strap firmly to purse with one side of strap on the inside and the other side of strap on the outside of purse.

Sew button to the front side of purse in the center of Row 18. Whipstitch closure strap to the center back of purse using the ch-6 loop as the buttonhole. Weave in ends.

ABBREVIATIONS / REFERENCES Click for explanation and illustration	
<pre>beg = begin(s)(ning)</pre>	ch(s) = chain(s)
rnd(s) = round(s)	RS = right side
sc = single crochet	st(s) = stitch(es)

Learn to crochet instructions: http://learnToCrochet.LionBrand.com

Every effort has been made to have the knitting and crochet instructions accurate and complete. We cannot be responsible for variance of individual knitters and crocheters, human errors, or typographical mistakes.



*<u>Lion Suede</u> (Article #210) A luxuriously soft yarn with a suede finish. Bulky Weight; 100% Polyester Solids are packaged in 3 oz/85g (122 yd/110 m) skeins, prints are packaged in 2 3/4 oz [78 g]/111 yd [101 m] balls



*<u>Wool-Ease® Chunky</u> (Article #650) is a bulky weight yarn -- a little heavier than original (worsted weight) Wool-Ease, but not as heavy as (super chunky weight) Wool-Ease Thick & Quick. It works up quickly and easily, yet is not really bulky. 80% Acrylic, 20% Wool. Packaged in 5 oz/140g; 153 yd/140m skeins.

We want your project to be a success! If you need help with this or any other Lion Brand pattern, e-mail support is available 7 days per week. Just click <u>here</u> to explain your problem and someone will help you!

For hundreds of free patterns, visit our website www.LionBrand.com
To order visit our website www.e-yarn.com or call: (800) 258-YARN (9276) any time!

Copyright ©1998-2005 Lion Brand Yarn Company, all rights reserved. No pattern or other material may be reproduced -- mechanically, electronically, or by any other means, including photocopying -- without written permission of Lion Brand Yarn Company. If you would like to send a copy of this page to someone, click here and we will be happy to do it for you.