Free Knitting Pattern
Lion Brand® Modern Baby®
Fishy Wishy Scarf
Pattern Number: L40150

Designed by Amy Bahrt

Lion Brand® Modern Baby®
Fishy Wishy Scarf
Pattern Number: L40150

SKILL LEVEL: Easy (Level 2)

SIZE: One Size

About 4 1/2 x 42 in. (11.5 x 106.5 cm), including tentacles.

CORRECTIONS: None as of Jun 21, 2014. To check for later updates, click here.

MATERIALS

- 924-098 Lion Brand Modern Baby: Cream
  1 Ball (A)
- 924-109 Lion Brand Modern Baby: Blue
  2 Balls (B)
- 924-113 Lion Brand Modern Baby: Red
  1 Ball (C)
- 924-148 Lion Brand Modern Baby: Turquoise
  1 Ball (D)
- 924-158 Lion Brand Modern Baby: Yellow
  1 Ball (E)
- Lion Brand Knitting Needles- Size 6 [4.00 mm]
- Lion Brand Double-Pointed Needles - Size 6
- Lion Brand Crochet Hook - Size G-6 (4 mm)
- Lion Brand Large-Eye Blunt Needles (Set of 6)

Modern Baby (Article #924). 50% Acrylic, 50% Nylon; package size: 2.60oz/75.00 gr. (173yds/158m) pull skeins

GAUGE:

20 sts + 36 rows = 4 in. (10 cm) in Garter st (k every row).

When you match the gauge in a pattern, your project will be the size specified in the pattern and the materials specified in the pattern will be sufficient. The needle or hook size called for in the pattern is based on what the designer used, but it is not unusual for gauge to vary from person to person. If it takes you fewer stitches and rows to make your swatch, try using a smaller size hook or needles; if more stitches and rows, try a larger size hook or needles.

STITCH EXPLANATION:

Chain Stitch

Thread needle and bring from back to front through piece. *Hold short length of yarn on front forming a small loop. Insert needle back into where it last came out, do not pull tight. Bring needle back through work and through small loop; repeat from * until chain is desired length.

French Knot

Thread needle and bring from back to front through knitted piece. Wrap yarn around needle 3 times, insert needle back into knitted piece close to where it emerged. Tighten knot.

kfb (knit in front and back) Knit next st without removing it from left needle, then k through back of same st – 1 st increased.

Knitted Cord (on double pointed needles) Working with 2 double pointed needles, cast on specified number of sts. Knit the sts. Do not turn work. *Slide sts to other end of needle and knit them, pulling yarn tightly across the back of the work, (do not turn work); rep from * until cord measures desired length.

NOTES:

1. Scarf is worked in one piece in Garter st (k every row).
2. Fish and octopus charts are worked in intarsia colorwork, following chart. Use a separate ball of yarn for each color section. Twist yarns on WS to prevent holes. Do not carry unused color(s) across WS of work.
3. When working from charts, work in Garter st and read RS rows from right to left and WS rows from left to right.
4. When you see "– 12 sts" in the instructions, this lets you know how many sts you will have at the end of that specific row.

SCARF

With straight needles and C, cast on 12 sts.

Knit 2 rows.

Increase Row 1 (RS): K1, kfb, knit to last 2 sts, kfb, k1 – 14 sts at the end of this row.

Row 2: Knit.

Row 3-12: Rep Rows 1 and 2 – 24 sts at the end of Row 12.

With C, work in Garter st (k every row) until piece measures about 4 1/2 in. (11.5 cm) from beg.

Octopus Chart

Next Row (RS): With A, work Row 1 of Octopus Chart across row.

Continue to work in Garter st and chart until 14 rows of Octopus Chart have been completed.

With B only, work in Garter st until piece measures about 33 in. (84 cm) from beg, end with a WS row as the last row you work.

Fish Chart

Next Row (RS): With B, k4, work Row 1 of Fish Chart across next 16 sts, with B, k4.

Keeping first and last 4 sts in B and rem sts in Fish Chart, work in Garter st until 14 rows of Fish Chart have been completed.

With B only, work in Garter st for 4 rows.

Decrease Row (RS): K1, k2tog, k to last 3 sts, k2tog, k1 – 22 sts.

Next Row: Knit.

Rep last 2 rows until 12 sts rem.

Bind off.

FINISHING

Octopus Tentacles (make 5)

With double pointed needles and C, cast on 6 sts. Work in knitted cord until piece measures about 4 in. (10

cm) from beg. Cut yarn, leaving a long yarn tail. Thread tail through rem sts and pull to gather. Knot securely.

Sew tentacles evenly spaced along edge of octopus.

With A, embroider a line of chain st across Row 6 of Octopus Chart.

With D, embroider French knot eyes on octopus.

Fish Lips

With crochet hook and F, chain 8.

Fasten off.

Wrap a strand of F tightly around center and pull to gather. Sew lips to fish. With B, embroider a French knot eye on fish. With D, embroider chain st around outside edge of fish.

Weave in ends.

Octopus Chart

24 Stitches

Fish Chart

16 Stitches

Stitch Key

A
B
D

ABBREVIATIONS / REFERENCES	
Click for explanation and illustration	
beg = begin(s)(ning)	k = knit
k2tog = knit 2 together	rem = remain(s)(ing)
rep = repeat(s)(ing)	RS = right side
st(s) = stitch(es)	WS = wrong side

Every effort has been made to have the knitting and crochet instructions accurate and complete. We cannot be responsible for variance of individual knitters and crocheters, human errors, or typographical mistakes.

We want your project to be a success! If you need help with this or any other Lion Brand pattern, e-mail support is available 7 days per week. Just click here to explain your problem and someone will help you!

For thousands of free patterns, visit our website www.LionBrand.com
To order visit our website www.lionbrand.com **or call: (800) 258-YARN (9276) any time!**

When in New York City, visit the Lion Brand Yarn Studio where we have the largest selection of our yarns anywhere and over 100 classes and events monthly.
34 West 15th Street, NY, NY 10011