



Free Crochet Pattern
Lion Brand® Heartland®
Filet Crochet Shawl
Pattern Number: L40668



SKILL LEVEL – Easy+

SIZES

Finished Width 50 in. (127 cm), across top edge

Finished Length 25 in. (63.5 cm)

MATERIALS

- Lion Brand® Heartland® (Art. #136)
 - 144 Kenai Fjords 2 balls
 - or color of your choice
- Lion Brand® crochet hook size J-10 (6 mm)
- Lion Brand® stitch markers
- Lion Brand® large-eyed blunt needle



GAUGE

14 dc + 6 rows = about 4 in. (10 cm).

BE SURE TO CHECK YOUR GAUGE.

NOTES

1. Shawl is worked back and forth in rows beg at center top.
2. Markers are placed and increases are worked at markers to shape the Shawl.
3. An edging is worked around the outer edge of Shawl.

SHAWL

Wrap yarn around index finger. Insert hook into ring on finger, yarn over and draw up a loop. Carefully slip ring from finger and work the stitches of Row 1 into the ring.

Row 1: Ch 4 (counts as first dc, ch 1 in this row and in all following rows), dc in ring, (ch 1, dc in ring) 3 times – you will have 5 dc and 4 ch-1 sps. Gently but firmly, pull yarn tail to tighten center of ring.

Row 2: Ch 4, turn, dc in first dc, *ch 1, sk next ch-1 sp, (dc, ch 1, dc) in next dc; rep from * to turning ch-sp, ch 1, dc in turning ch-sp – 9 dc and 8 ch-1 sps.

Row 3: Ch 4, turn, sk first ch-1 sp, (dc, ch 1, dc) in next dc, *ch 1, sk next ch-1 sp, dc in next dc, ch 1, sk next ch-1 sp, (dc, ch 1, dc) in next dc; rep from * to turning ch-sp, ch 1, dc in turning ch-sp – 13 dc and 12 ch-1 sps.

Row 4: Ch 4, turn, sk first ch-1 sp, (dc, ch 1, dc) in next dc, *(ch 1, sk next ch-1 sp, dc in next dc) twice, ch 1, sk next ch-1 sp, (dc, ch 1, dc) in next dc; rep from * twice, ch 1, sk next ch-1 sp, dc in next dc, ch 1, dc in turning ch-sp – 17 dc and 16 ch-1 sps.

Row 5: Ch 4, turn, sk first ch-1 sp, dc in next st, ch 1, sk next ch-1 sp, (dc, ch 1, dc) in next dc, *(ch 1, sk next ch-1 sp, dc in next dc) 3 times, ch 1, sk next ch-1

For thousands of free patterns, visit our website www.LionBrand.com

To order visit our website www.lionbrand.com or call: (800) 258-YARN (9276) any time!

Copyright ©1998-2016 Lion Brand Yarn Company, all rights reserved.

No pattern or other material may be reproduced -- mechanically, electronically, or by any other means, including photocopying - without written permission of Lion Brand Yarn Company.

sp, (dc, ch 1, dc) in next dc; rep from * twice, ch 1, sk next ch-1 sp, dc in next dc, ch 1, dc in turning ch-sp – 21 dc and 20 ch-1 sps.

Row 6: Ch 4, turn, sk first ch-1 sp, dc in next dc, ch 1, sk next ch-1 sp, (dc, ch 1, dc) in next dc, place a marker in last dc made, *(ch 1, sk next ch-1 sp, dc in next dc) 4 times, ch 1, sk next ch-1 sp, (dc, ch 1, dc) in next dc, place a marker in last dc made; rep from * twice, (ch 1, sk next ch-1 sp, dc in next dc) twice, ch 1, dc in turning ch-sp – 25 dc and 24 ch-1 sps.

Rows 7-10: Ch 4, turn, sk first ch-1 sp, dc in next dc, *(ch 1, sk next ch-sp, dc in next dc) to ch-sp before next marked dc, ch 1, sk next ch-sp, (dc, ch 1, dc) in marked dc, move marker to last dc made; rep from * 3 times, (ch 1, sk next ch-sp, dc in next dc) to turning ch-sp, ch 1, dc in turning ch-sp – 41 dc and 40 ch-1 sps at the end of Row 10.

Rows 11-14: Ch 5 (counts as first dc, ch 2), turn, sk first ch-sp, dc in next dc, *(ch 2, sk next ch-sp, dc in next dc) to ch-sp before next marked dc, ch 2, sk next ch-sp, dc in marked dc, move marker to last dc made; rep from * 3 times, (ch 2, sk next ch-sp, dc in next dc) to turning ch-sp, ch 2, dc in turning ch-sp – 41 dc and 40 ch-2 sps.

Rows 15 and 16: Ch 5 (counts as first dc, ch 2), turn, sk first ch-sp, dc in next dc, *(ch 2, sk next ch-sp, dc in next dc) to ch-sp before next marked dc, ch 2, sk next ch-sp, (dc, ch 2, dc) in marked dc, move marker to last dc made; rep from * 3 times, (ch 2, sk next ch-sp, dc in next dc) to turning ch-sp, ch 2, dc in turning ch-sp – 49 dc and 48 ch-2 sps at the end of Row 16.

Rows 17 and 18: Rep Row 11 twice.

Rows 19 and 20: Rep Rows 15 and 16 – 57 dc and 56 ch-2 sps at the end of Row 20.

Rows 21-24: Ch 6 (counts as first dc, ch 3), turn, sk first ch-sp, dc in next dc, *(ch 3, sk next ch-sp, dc in next dc) to ch-sp before next marked dc, ch 3, sk next ch-sp, dc in marked dc, move marker to last dc made; rep from * 3 times, (ch 3, sk next ch-sp, dc in next dc) to turning ch-sp, ch 3, dc in turning ch-sp – 57 dc and 56 ch-3 sps.

Rows 25 and 26: Ch 6 (counts as first dc, ch 3), turn, sk first ch-sp, dc in next dc, *(ch 3, sk next ch-sp, dc in next dc) to ch-sp before next marked dc, ch 3, sk next ch-sp, (dc, ch 3, dc) in marked dc, move marker to last dc made; rep from * 3 times, (ch 3, sk next ch-sp, dc in next dc) to turning ch-sp, ch 3, dc in turning ch-sp – 65 dc and 64 ch-3 sps at the end of Row 26.

Remove markers.

Rows 27-30: Ch 6 (counts as first dc, ch 3), turn, sk first ch-sp, dc in next dc, *ch 3, sk next ch-sp, dc in next dc; rep from * to turning ch-sp, ch 3, dc in turning ch-sp – 65 dc and 64 ch-3 sps.

Row 31: Ch 3 (counts as first dc), turn, 3 dc in first ch-sp, dc in next dc, *3 dc in next ch-sp, dc in next dc; rep from * to turning ch-sp, 4 dc in turning ch-sp – 257 dc.

Row 32: Ch 5 (counts as first dc, ch 2), turn, sk first 3 dc, dc in next dc, ch 2, sk next dc, dc in next dc, *(ch 2, sk next 2 dc, dc in next dc) twice, ch 2, sk next dc, dc in next dc; rep from * to 2 dc before turning ch, ch 2, sk next 2 dc, dc in top of turning ch – 97 dc and 96 ch-2 sps.

For thousands of free patterns, visit our website www.LionBrand.com

To order visit our website www.lionbrand.com or call: (800) 258-YARN (9276) any time!

Copyright ©1998-2016 Lion Brand Yarn Company, all rights reserved.

No pattern or other material may be reproduced -- mechanically, electronically, or by any other means, including photocopying - without written permission of Lion Brand Yarn Company.

Row 33: Ch 3 (counts as first dc), turn, *2 dc in next ch-sp, dc in next dc, (ch 2, sk next ch-2 sp, dc in next dc) 4 times; rep from * to turning ch-sp, 3 dc in turning ch-sp – 137 dc and 76 ch-2 sps.

Row 34: Ch 5 (counts as first dc, ch 2), turn, sk first 3 dc, dc in next dc, (ch 2, sk next ch-2 sp, dc in next dc) 4 times, *ch 2, sk next 2 dc, dc in next dc, (ch 2, sk next ch-2 sp, dc in next dc) 4 times; rep from * to 2 dc before turning ch, ch 2, sk next 2 dc, dc in top of turning ch – 97 dc and 96 ch-2 sps.

Row 35: Rep Row 33.

Row 36: Ch 3 (counts as first dc), turn, sk first dc, dc in next 3 dc, 2 dc in next ch-sp, dc in next dc, (ch 2, dc in next dc) twice, 2 dc in next ch-sp, *dc in next 4 dc, 2 dc in next ch-sp, dc in next dc, (ch 2, dc in next dc) twice, 2 dc in next ch-sp; rep from * to 3 dc before turning ch, dc in next 3 dc, dc in top of turning ch – 209 dc and 38 ch-2 sps.

Row 37: Ch 3 (counts as first dc), turn, sk first dc, dc in next 6 dc, *(2 dc in next ch-2 sp, dc in next dc) twice, dc in next 9 dc; rep from * to turning ch, dc in top of turning ch – 289 dc.

Do not fasten off.

Edging

Rnd 1: Ch 1, turn, sc in each st to turning ch, 3 sc in turning ch-sp; work 2 sc in the end of each row all the way across top edge, 2 sc in corner; join with sl st in first sc.

Fasten off.

FINISHING

Weave in ends.

ABBREVIATIONS

beg = begin(ning)

ch = chain

ch-sp(s) = chain space(s) previously made

dc = double crochet

rep = repeat

sc = single crochet

sk = skip

sl st = slip stitch

sp(s) = space(s)

st(s) = stitch(es)

Every effort has been made to produce accurate and complete instructions. We cannot be responsible for variance of individual knitters or crocheters, human error, or typographical mistakes.

For thousands of free patterns, visit our website www.LionBrand.com

To order visit our website www.lionbrand.com or call: (800) 258-YARN (9276) any time!

Copyright ©1998-2016 Lion Brand Yarn Company, all rights reserved.

No pattern or other material may be reproduced -- mechanically, electronically, or by any other means, including photocopying - without written permission of Lion Brand Yarn Company.