

Free Crochet Pattern **Lion Brand® Rewind** Artwall Cardigan Pattern Number: L80352

Designed by Teva



Lion Brand® Rewind Artwall Cardigan Pattern Number: L80352

SKILL LEVEL - Easy+

SIZES

S (M, L, 1X/2X)

Finished Bust About 44 (48, 52, 58) in. (112 (121, 132, 147.5) cm) **Finished Length** About 30 in. (76 cm)

Note: Pattern is written for smallest size with changes for larger sizes in parentheses. When only one number is given, it applies to all sizes. To follow pattern more easily, circle all numbers pertaining to your size before beginning.

MATERIALS

- Lion Brand® Rewind (Art. #523)
 - 138 Current Situation 5 (6, 6, 7, 8) balls
- Lion Brand® crochet hook size K-10.5 (6.5 mm)
- Lion Brand® stitch markers
- Lion Brand® large-eyed blunt needle



GAUGE

16 dc + 8 rows = about 6 in. (15 cm). BE SURE TO CHECK YOUR GAUGE.

NOTES

- 1. Cardigan is made in 6 pieces: 4 identical Panels for the body and 2 Sleeves.
- 2. Pieces are crocheted together from RS to create decorative seams.

PANELS (make 4)

Ch 31 (34, 37, 40).

Row 1: Dc in 4th ch from hook (3 skipped ch count as dc), and in each ch across—29 (32, 35, 38) sts.

Row 2: Ch 3, turn, skip first dc, dc in each dc across, working last dc in top of turning ch.

Rep Row 2 until piece measures about 30 in. (76 cm) from beg. Fasten off.

SLEEVES (make 2)

Ch 31 (34, 37, 40).

Row 1: Dc in 4th ch from hook (3 skipped ch count as dc), and in each ch across—29 (32, 35, 38) sts.

Row 2: Ch 3, turn, skip first dc, dc in each dc across, working last dc in top of turning ch.

Lion Brand® Rewind Artwall Cardigan Pattern Number: L80352

Rep Row 2 until piece measures about 10 (10, 8, 8) in. (25.5 (25.5, 20.5, 20.5) cm) from beg.

Shape Sleeve

Row 1 (Increase Row): Ch 3, turn, dc in first dc (1 st increased), dc in each dc across, working last dc in top of turning ch -30 (33, 36, 39) **Row 2 (Increase Row):** Rep Row 1 -31 (34, 37, 40) sts.

Deur 2. Ch 2. akin firet de de in each de carece werking leet de in ten

Row 3: Ch 3, skip first dc, dc in each dc across, working last dc in top of turning ch.

Rep Rows 1-3 for 3 (3, 4, 4) times more – 37 (40, 45, 48) sts, then rep Row 3 until piece measures about 18 in. (45.5 cm) from beg.

Fasten off.

FINISHING

Note: All pieces are joined on the RS to make decorative seams

Right Front and Back

Align 2 Panels with WS together, matching foundation and final rows.

Count 14 sts from right edge and working through both thicknesses, join yarn with a sl st.

Ch 1, working through both thicknesses, sc evenly spaced to end of Panel, leaving 14 skipped sts unworked.

Note: The top front corner folds down to form collar.

Fasten off.

Join Sleeve

Place markers on left side edge of front and back, 7 (7 1/2, 8 1/2, 9) in. (18 (19, 21.5, 23) cm) below shoulder seam.

From RS, and working through both thicknesses, join yarn with a sl st and work sc evenly spaced to join top of Sleeve to Left Front and Back between markers.

Side and Sleeve Seams

From RS and working through both thicknesses, join yarn with a sl st. Work sc evenly spaced to join side and Sleeve seams, leave about 6 in. (15 cm) open at lower edge for side slits.

Join Left Front, Back and remaining Sleeve in same way.

Lion Brand® Rewind Artwall Cardigan Pattern Number: L80352

Sleeve Edging

From RS, join 2 strands of yarn held together with a sl st in wrist edge of Sleeve at Sleeve seam.

Ch 1, work sc evenly spaced around Sleeve edge; join with sl st in first sc. Fasten off.

Work same edging on opposite Sleeve.

Join Back Panels

Match Left and Right Back Panels and join with sc seam on RS.

Outside Edging

From RS, join 2 strands of yarn held together with a sl st into either shoulder seam.

Work edging same as Sleeve edging around entire outside edge of Cardigan including slits, working 2 sc at each corner; join with sl st in first sc. Fasten off.

Weave in ends.

BELT (optional)

With 2 strands of yarn held together, make a chain in desired length.

Row 1: Sc in 2nd ch from hook and in each ch across.

Fasten off.

Weave in ends.

ABBREVIATIONS

beg = begin(ning)(s)

ch = chain

dc = double crochet

RS = right side

sc = single crochet

sl st = slip stitch

st(s) = stitch(es)

WS = wrong side

Every effort has been made to produce accurate and complete instructions. We cannot be responsible for variance of individual crafters, human error, or typographical mistakes.

