



LION BRAND® WOOL-EASE® SPORTWEIGHT Child's Knitted Jumper



Skill Level: Advanced Beginner

SIZE

1 (2, 3) years. **Finished Chest size** 21 (24, 26 1/2)"

MATERIALS

- LION BRAND Wool-Ease Sportweight
- 1 (2, 2) balls #099 Fisherman or color of your choice
- Size 6 (4 mm) knitting needles OR SIZE TO OBTAIN GAUGE
- Size 6 (4 mm) 24" long circular knitting needle
- Size F-5 (3.75 mm) crochet hook
- Four 3/4" (19 mm) buttons

GAUGE

20 sts and 28 rows = 4" (10 cm). BE SURE TO CHECK YOUR GAUGE.

PATTERN STITCHES

Fishtail Lace (knitted in-the-rnd with a multiple of 8 sts)

Rnd 1 (RS) *K 1, yo, k 2, sl1-k2tog-ssso, k 2, yo; rep from * around.

Rnds 2, 4 & 6 Knit.

Rnd 3 K 2, *yo, k 1, sl1-k2tog-ssso, k 1, yo, k 3; rep from * around, end last rep k 1 instead of k 3.

Rnd 5 K 3, *yo, sl1-k2tog-ssso, yo, k 5; rep from * around, end last rep k 2 instead of k 5.

Twisted Rib Pattern (multiple of 2 sts)

Rnd or Row 1 *K 1 through back loop, p 1; rep from *.

Rnd or Row 2 *K 1, p 1; rep from *.

Rep Rnds or Rows 1 & 2 for Twisted Rib Pat.

BODY

With circular needle, cast on 208 (240, 264) sts. Join and place a marker for beg of rnd. Work Fishtail Lace Pat Rows 1-6 twice, then rep Rows 5 & 6, 4 (5, 6) times. Cont in St st (= k every rnd) until piece measures 9 1/2 (10 1/4, 11 1/2)" from beg. **Waist: Next rnd** K2tog around -- 104 (120, 132) sts. **Bib** Work 2 rnds in Twisted Rib Pat. **Divide for front and back** Using straight knitting needles (or working back-and-forth on circular

© 1998, 1999, 2000 Lion Brand Yarn Company, 34 West 15th Street, New York, New York 10011
Call TOLL-FREE 1-800-258-YARN

needles) work 52 (60, 66) sts for front, place rem 52 (60, 66) sts on a holder for back.
Front: Shape armholes Working back and forth in Twisted Rib Pat, bind off 2 sts at beg of next 2 rows. Dec 1 st each side every other row 3 (4, 4) times, then dec 1 st at end of next row -- 41 (47, 53) sts. Work even in Twisted Rib Pat until bib measures 2 1/2 (3, 3 1/2)", ending with a WS row. **Shape neck** Cont in Twisted Rib Pat, work 16 (18, 21) sts, join a new ball of yarn and bind off center 9 (11, 11) sts for neck, work to end of row. Working both sides at the same time with separate balls of yarn, cont in Twisted Rib Pat dec 1 st at each neck edge every other row 5 times. Work even on rem 11 (13, 16) sts until bib measures 5 1/2 (6, 6 1/2)". **Buttonhole row** Rib 2 (3, 3), yo, k2tog, rib 3 (3, 6), yo, k2tog, rib to end. Rib 3 more rows. Bind off rem sts each side.

BACK

Work as for front, however, beg neck shaping when bib measures 3 (3 1/2, 4)". Complete as for front omitting buttonholes.

FINISHING

Crochet Edge With RS facing, using crochet hook, join yarn with a slip st at bottom of armhole, *3 sc, ch 3, slip st in top of last sc; rep from * around armhole, shoulder and neck on front and back. Fasten off. Sew on buttons opposite buttonholes

ABBREVIATIONS	
beg = begin(ning)	rep = repeat
ch = chain	rnd(s) = round(s)
cont = continu(e)(ing)	RS = right side
dec = decreas(e)(s)(ing)	sc = single crochet
k = knit	sl = slip
p = purl	st(s) = stitch(es)
pat = pattern	tog = together
psso = pass slip stitch over	WS = wrong side
rem = remain(s)(ing)	yo = yarn over

Every effort has been made to have the knitting and crochet instructions accurate and complete. We cannot be responsible for variance of individual knitters and crocheters, human errors, or typographical mistakes.

To order call: (800) 258-YARN (9276)